

Xlite

There is so many communication softwares with diferents technology out there that can connect to our servers, sometime configuration is a bit painless but the voice quality and the way the data is passing through network can be drastically different from one software to an other also remember to use a good microphone the best is to use a good headset/microphone when communicating, after finishing your call just unplug your headset to be able to hear your computer ringing when someone is calling you !!

in Order to connect to our servers from your boat u need to install and run an SIP compliant software to register with us and use your account.

After several test we did choose X-Lite with the GSM Codec (best alorythm for compression and voice quality over wifi) the following is for Windows Xp/Vista isntallation for other platform Linux or Mac several others free software are on the market and ready to connect with us just ask us we will assist you and provide you with information.

First of all you need to download the software by clicking the link below :

Voip SoftPhone Xlite software with GSM Codec

Xlite manual in PDF format

Execute the installation by following step by step :

1) Click next

2) Click Next

3)Click Next

4)Click Next

5)Click Finish 6)Click NO

7)IMPORTANT

Click No 8)Click Add

9)Put Your Name in display Name

Put the extension number we gave

to you in User name

Put The password we provided to you

Put telecodex.com in Domain Field

Click on Proxy and under adress

put telecodex.com

Click on OK

10)in This example John Brown
using extension 2127 with a
password just created his account

11)Click on Close (information displayed
will be different for you)

12)The software should have been
register successfully with our servers,
your username extension number
should appear and the word ready
should be there as well

****IMPORTANT AS OF APRIL 2009 :

right click with your mouse button
on the screen of the softphone choose:

- 1) sip account settings
- 2)cliquer sur properties
- 3)cliquer sur topology
- 4)ON STUN SERVER click on

USE SPECIFED SERVER

- 5) type : stun.telecodex.com
- 6)at bottom click OK
- 7)CLICK on Close

Your phone will

register on our network

13)Taking Off AUTO upgrade, you
have to right click with
your mouse button on
the screen of the software
choose Options

14)Take off the option "Prompt me
when an upgrade is available"
and than click OK

Now you can start to

receive calls and make
calls as well. Enjoy